


Here is our first release of the year 2021 – welcome RadExPro 2021.1!


The main novels are as following:

• New stand-alone **Source-Receiver Repositioning** module allows adjusting positions of source/receiver points basing on the first arrivals. You can typically use this to correct OBN positions offshore or SP positions on-land.



Trace: - Sample: - Amplitude: - Time: - ms

Common receiver gather from an OBN. <u>Red line</u> is the theoretical first arrival calculated basing on the original positioning information, <u>green line</u> – the same after repositioning of the receiver.



Map of OBN positions: <u>red dots</u> – original positioning information, <u>green dots</u> – resulting positions adjusted by the Source-Receiver Repositioning module.

• **3D Stolt F-K Migration** module can now migrate with variable velocity. Velocity may vary both vertically and laterally. The algorithm implements classical approach, stretching time axis of each individual trace.

) Constant velocity		Select velocity model		×
Variable velocity (r	n/ms)	Select velocity model		
Input dataset		Velocity		
Output dataset		Velocity source		1
		C Single velocity function		
Migration Paran	neters	500-1000:2.5, 2000:2.7, 3000:2.9		
Max. frequency t	-			
Frequency declinin		O Use file:		
	. dip (degrees)		Browse	
		Database - picks vel01	Browse	
Dip s	lope (degrees)		Browse	
		C Velocity dataset	DIOWSE	
Gird		C VSP file	Browse	
Manual		Velocity domain	locity type	_
	Origin X		RMS C Interval	
	Origin Y			

• Both **Data Filter** module and **filter on pipes in graphic mode** can now load a list of particular traces from a text file. In this case, the edit field of the module shall contain a string with a list of trace headers defining how the columns of the file are to be interpreted.


🔁 Data Filter	×					
🔿 No filter						
O Match selection						
O not match selection						
R_LINE : REC_SLOC						
✓ Take values from file: jects\My Project_0809\ist_of_dead_receivers.txt						
OK Cancel						
🗐 *list_of_dead_receivers.txt – — 🗆 🗙						
<u>Ф</u> айл <u>П</u> равка Фор <u>м</u> ат <u>В</u> ид <u>С</u> правка						
1101 5130 ^						
1101 5140						
1101 5141						
1101 5153						
1101 5167						
1101 5204						
1101 5223						
1101 5232						
1105 5101						
1105 5106						
1105 5109						
1105 5112						
1105 5113 1105 5114						
Стр 1 100% Windows (CRLF) UTF-8						

In this example, the first column in the 'list_of_dead_receivers.txt' file contains R_LINE values, and the second column contains REC_SLOC values of dead receiver locations. Traces from the locations in the list will not pass the filter and will be excluded from the flow.

• In the **Interactive QC** module now, you can use trace filter to limit a range of traces to be loaded and displayed on the maps.

Interactive QC*	×
Input dataset	
Area1\for_study_RAW_edt	
Note: the dataset must be sorted by FFID	Read interval: 120 sec
Headers: FFID, OFFSET	Add
Selection: 21-2000:100-500	

- Now, you can export **Interactive QC** visual settings into a file and import it to another project.
- In the **Pre/Post Stack Kirchhoff Time** module parameters now, you can indicate nominal spacing between traces in the along-inline (DX) along-crossline (DY) directions. These values are to be used for anti-aliased filter calculation.
- In the **3D Volume Viewer** module in addition to Ctrl-Up and Ctrl-Down, now you can control vertical scale explicitly using 'Trace scale stretch factor' value.



• **NMO/NMI** module now works significantly faster due to optimized parallelization.

- We **removed the maximum limit of 300 trace headers** in a project. Now, if you need more, you can create more.
- **3D Volume Zero-Padding** module now supports replicas. You can use replica variables for i/o dataset names as well as for inline/xline output ranges. Besides, the resulting datasets now have correct DT and NUMSMP headers as well as a history record.
- Filter on DB Navigator tab is now register independent.
- In the *Real-Time* configuration of the software, **Real-Time SEG-D Input** and **Real-Time SEG-D Input (Rev.3)** modules can now scan the SEGD files written to subfolders of the first level, not just the parent folder.

≽ Seg-D Input (Rev.3)		×				
File(s) Parameters	Remap Log					
Listen directory: C:/p	rojects/proj1/data					
☑ Listen subdirectories						
Mask:	*.sgd; *.ffid File delay (files): 0 ~					
Real-Time read order:	Incremental name \checkmark End of line timeout (s): 0					
Take files already present in listen directory						

- Some issues were fixed:
 - If one loads a dataset by Trace Input with 'Get all' option selected and then exports it from the flow to an rdx-file, this file then crashes Dataset Import --FIXED!
 - DB Navigator sorting datasets by size is incorreect FIXED!
 - RMS to Interval velocity conversion in Velocity Manipulation module fails -FIXED!
 - Bug in Seismic Display in frame mode + variable trace distance (no display after the 1st frame) - FIXED!
 - DB Navigator -- 'Empty' command of the dataset context menu clears dataset history - FIXED!
 - Geometry Spreadsheet -- if one uses Trace Header Math tool with an expression like H3=H1+H2 without displaying H1 header on the screen, this operation makes the whole H1=0 - FIXED!

As always, if you are on maintenance, please contact us at <u>support@radexpro.com</u> and get your free update.

IMPORTANT!: Please, note that for most of you, this update will require updating licenses in your dongles. Please, follow the instruction below to generate a c2v-file for each of your dongles and attach these files to the e-mail with the update request.

LICENSE UPDATE INSTRUCTION:

1. Connect the dongle to your computer and run RUS_WXDXI utility (it is installed together with the program and is available through Start menu in RadExPro program group).

2. In the dialog that opens, click the Collect Information button on the Collect Status Information tab, save the file with key information (*.c2v).

3. Attach this file to the e-mail with the update request and sent this e-mail to support@radexpro.com.

4. We will generate a new license and send it to you. After that, in the same utility you will need to select the license file on the Apply License File tab and press Apply Update to apply it to the dongle.